

Product Search with Static Content Page Results

Overview

In its traditional use, the Search tool ('Product Search Widget') on your site (usually located in the Themes Layout template) enables website visitors to look for products. They type in keywords, usually product names or codes, and the search results lists products you sell based on those keywords. Content (web) pages that contain those keywords are not automatically indexed by the system and so, are not included in the results. (Example 1.)


It is now increasingly popular for visitors to a selling site to use the Search facility to find static content such as product guides, how-to articles or info about firmware upgrades for the device they purchased. You can configure the search tool to include content pages in search results.

On this page:

- [Overview](#)
- [How does Include Content Search work?](#)
- [Step-by-step guide](#)
 - [1. Turn on Content Search](#)
 - [2. Configure Indexing Settings](#)
 - [3. Set Product Search widget to include content pages](#)
 - [4. Customise the Page Content Search Result template \(optional\)](#)
 - [5. Configure the Product List Title widget](#)
 - [6. Turn off 'Direct Product Display'](#)
 - [7. Test the reconfigured search for content](#)
- [Additional Information](#)
 - [Minimum Version Requirements](#)
- [Related help](#)

Choose to include such content if you wish, or even add another Search facility just for finding such pages. (Example 2.)

Example 1. Product Search suggestions - results with products only



Search Results with no Content page search

Home > Search "tennis"

Displaying 7

Search Results

Grid List

Grid List



Head Ti52 Tennis Racquet
CV117

In Stock 116  Available for Delivery  Available for Pickup

\$79.99
inc GST
RRP \$79.99 (Each)

0 - + 

☐ Add to Compare



PENN Championship Tennis Balls
CV118

Available in various quantities. Price will reflect number of balls/cans.

Available on Back Order for Delivery  Unavailable for Pickup

Number

0 - + 

☐ Add to Compare

> **Product Options**

☐ Add to Compare

How does Include Content Search work?


By default, content pages are not included in Product Search. When the search facility is set to include such pages, the search engine will index those that are publicly accessible so they can be findable.

Step-by-step guide


Follow these steps to configure 'Include Content Search' for your site.

1. Turn on Content Search

1. To turn on the *Content Search* feature, navigate to **Settings** *Feature Management* **Content**
2. In the list of features, toggle on **Content Search** and click **Configure**.



3. In the 'Content Search Settings' window, toggle on *Enable Content Search Feature*.




4. In *Page Content Reindex Task Start Date*, set the schedule to a few minutes in the future.
5. The *Page Content Reindex Task Period in Minutes* sets the amount of time before the system will reindex content pages after the date/time entered in Step 4. Accept the default or enter an alternative.
6. Click **Save and Exit** to save and close the window.


2. Configure Indexing Settings

Content pages on your site need to be analysed and added to the search engine's database of web pages included in searches. The system takes advantage of [Lucene](#)'s indexing and searching features to maximise its search capabilities.


1. In CMS, navigate to **Advanced Settings** *Lucene Search Settings*.
2. Select the **Index Settings** tab.
3. To enable indexing, tick the **Enabled** checkbox.



4. Tick **Perform Partial Word Searches** (recommended). If this is enabled, as the user types in the search box, products linked to a partial (unfinished) word will be displayed. Leave this box unticked if you want the search to find the exact whole word entered. (**Note** - partial word search is not yet enabled for content pages.)



5. To save the settings, click **Update**.
6. Click the **Indexing** tab.
7. To reindex content pages, click the **Reindex Page Content** button.




 Every time you add a new content page or update an existing one to your site, the new content will only be searchable after reindexing.

3. Set Product Search widget to include content pages

The Product Search widget, which provides the search facility on your site, needs to be set to include content pages.

1. Navigate to **Content Page & Templates Theme Layout**.
2. Click the **Theme Layout** option.
3. Locate the **Product Search** widget and click **Edit**. In our example, this widget is under Zone:HeaderColumn2.



4. In the Product Search window, locate **Static Content Search** and select '**Include Static Content Search**'. (Note - if you are creating a search for content pages only, then select 'Static Content Search Only'.)

Product Search

Search...

General Options

Personalisation

Titles

Buttons

General Options

Description

Layer *

Static Content Search

Use Suggestions?

Use Product Suggestions?

All Pages

Include Static Content Search

Please Select ...

Disabled

Include Static Content Search

Static Content Search Only

5. In **Use Suggestions?**, decide whether the search box will display 'Suggestions', (i) or (ii). (For more on 'Use Suggestions', refer to [Product Search widget help](#).)


(i) **Toggle OFF:** no content page suggestions will be displayed as the user types in the Search box. After typing in the keyword(s), the user clicks 'Search' or presses 'Enter' to run the search.

cennid


Search

(ii) **Toggle ON:** web page suggestions will be displayed. Decide whether you want to set a maximum number of suggestions to display and go through the steps in either (a) or (b). (**Note** - if toggled on, both product and content suggestions must have maximum numbers.)

(a) Set no maximum number of results displayed




1. Ensure **Limit the Product and Static Content Result Returned?** is off.



2. Decide whether you want to use a 'Search Suggestions' heading. Scroll down to **Show Search Suggestions Heading?** and toggle on or off.




3. If show heading is on, you can edit the heading text. Click the **Titles** tab and edit the **Search Suggestions Heading Text**.




6. When you have finished configuring the widget, click **Save** and if your site is in Page Preview mode, click **Publish** to effect the changes on your site.

(b) Limit maximum




1. Ensure **Limit the Product and Static Content Result Returned?** is off.



2. In **'Static Content'**

If there are more results


3. To edit the text




4. Customise the Page Content Search Result template (optional)

You can edit the message that displays when a search yields no content results.


1. Navigate to **Content Page & Templates Other Page & Templates**.



2. Click **Edit** for the **Page Content Search Result Widget**.




3. Click the **Notification** tab and edit the message.



4. Click **Save**, and if you have your site set to **Page Preview**, then click **Publish** to effect the changes.

5. Configure the Product List Title widget

1. Navigate to **Content Page & Templates Products Product List**.
2. The **Product List Title** widget should be at the top of the **Product List** page. Click **Edit**.
3. The **Static Web Pages Found Message** displays text relating to search results for content pages. In the default message '{0} web page(s) found with contents related to your search', '{0}' = the number of pages found. Change the message to suit the tone of your business if required.



4. Click **Save** at the bottom of the page. If your site is set to 'Page Preview', click **Publish** to effect the changes on your site.

6. Turn off 'Direct Product Display'

Product Search can be set so that if the search finds only one product, the system will automatically redirect to its product page. This feature should be turned off for searches that include Content Pages.


To ensure it is off:

1. Navigate to **Settings Settings**.
2. Under the **'General'** tab, find **'Allow Redirect To ProdView For Single SearchResult'** and make sure it is not ticked.
3. If it is ticked, untick it and click **Update**.


7. Test the reconfigured search for content

Once Product Search with Content Page results is configured, you can test it to ensure it is as required for your website.

1. Perform a search to see what results are returned. What is displayed depends on the configurations entered in the **Product List Title** widget.



If your search returns no results, the "no results" message from the Product Search widget's notification tab is displayed.



2. If the keyword entered has product and content results, then pressing 'Enter' will list the web pages and products found. Clicking on the number, '4' in the example, will take you to the list of content pages where you click through to the content page.

[Home](#) > [Search "tennis equipment"](#)

Displaying 7

Search Results

4 web page(s) found with contents related to your search

Grid
 List

Grid
 List



Tennis Racquet
 CV116

In Stock 62
Available for Delivery
Available for Pickup

0

-

+

☐ Add to Compare

\$99.99
inc GST
 RRP \$99.99
(Each)

Add to cart



Head TiS2 Tennis Racquet
 CV117

In Stock 116
Available for Delivery
Available for Pickup

0

-

+

☐ Add to Compare

\$79.99
inc GST
 RRP \$79.99
(Each)

Add to cart

Additional Information

Minimum Version Requirements	4.23
Prerequisites	--
Self Configurable	Yes
Business Function	Site Optimisation
BPD Only?	Yes
B2B/B2C/Both	Both
Third Party Costs	n/a

Related help

- [Add Search Tool](#)
- [Product Search with Lucene Search Text Engine](#)
- [Lucene Introduction](#)
- [Product Search With Preview Widget](#)
- [Predictive Search](#)

